



<https://cloudblue.com>

[Documentation](#) [Developer Resources](#) [Connect SDK and Tools](#) [Python SDK](#) [Connect Processor SDK](#) [Use Cases](#)

Tier Config Processing



This article has been generated from the online version of the documentation and might be out of date. Please, make sure to always refer to the online version of the documentation for the up-to-date information.

Auto-generated at January 3, 2026



Overview

Tier Configuration (Tier Config) is used to assign configuration parameters to certain reseller accounts within the Distributor tiers hierarchy. In case the **Reseller Authorization** capability is enabled and **Tier** scope parameter is created, the system generates a Tier Configuration and a Tier Request (also referred to as Tier Configuration request) along with a subscription in the *Tier Setup* state. Note that the system can generate *setup* and *update* requests. Refer to the Tier Config module documentation for more details.

The initial status of a Tier Configuration is *Processing*, while the initial state of its associated Tier Request is *Pending*. Once your Tier Request is *approved*, your Tier Configuration will be automatically *activated* on the Connect platform.

Vendors can deploy the middleware to process Tier Requests and consequently activate Tier Configurations on the CloudBlue Connect platform. Follow the instructions below to configure the Processor for the aforementioned operations.

Prerequisites

- Your product is defined on the Connect platform.
- The Reseller Authorization capability is enabled.
- The Tier 1 scope parameter is created.
- A new subscription is required to process a tier request.
- The Processor SDK Template is successfully deployed.
- Your deployed Processor is properly configured.
- Vendor API configuration is presented.



Creating Tier Configurations

The following provides instructions on how to generate a Tier Configuration and its corresponding Tier Request on the CloudBlue Connect platform.

Enable Reseller Authorization

Before generating a subscription and creating a tier scope parameter, make sure that the **Reseller Authorization** capability is enabled for your specified product.

Proceed to the **General** section from your product profile page and switch to the **Capabilities** tab. Click the **Edit** button and turn on the **Reseller Authorization** capability.





Select **Tier 1** authorization structure. Note that *Tier 1* represents direct reseller of your customer.

Click the **Save** button to enable the required capability and save your specified authorization structure.



Create a Tier scope parameter

Next, it is necessary to create a parameter and select **Tier 1** scope within the parameter creation wizard.



Once your tier scope parameter is successfully created, your generated subscriptions require processing Tier Request and



activating Tier Configuration.

Generate a Subscription

Subscriptions for your specified product are generated by your customers via Prover marketplaces. However, Vendors can create a preview subscription to configure the Processor.

Create a subscription via the **Preview** section of your product profile page.

Alternatively, generate a preview subscription by accessing the **Subscriptions** module and clicking the **Create Subscription** button.

CloudBlue

Subscriptions

HELP

Front Street Inc.

Vendor - Robert Balboa

Subscriptions

DIRECTORY

FULFILLMENT

BILLING

+ CREATE SUBSCRIPTION

Active

REFRESH

1 FILTER APPLIED

1 SORT APPLIED

COLUMNS

Rows per page 10

1-1 of 1

SUBSCRIPTION	PRODUCT	MARKETPLACE	CUSTOMER	PERIOD	NEXT BILL	CREATED	STATUS
AS-6493-4392-4303 External ID: 6LQ0GED8L3	Tutorial Product PRD-640-516-332	Tutorial Marketp... MP-38661	Rice-Barrows TA-7031-3711-8413	1 month	04/25/2021 8:38 AM	02/25/2021 7:36 AM	Active

Rows per page 10

1-1 of 1



Follow the Subscription Creation documentation for more details.

Once a fulfillment request is successfully created and assigned to the *Tier Setup* state, the system generates a Tier Configuration and a Tier Request. Navigate to the **Tier Config** module to access your Tier Configurations and Tier Requests.



CloudBlue

Tier Config

HELP

11

Front Street Inc.
Vendor - Robert Balboa

Tier config

DIRECTORY

REQUESTS

All tier configs

REFRESH

FILTER

1 SORT APPLIED

COLUMNS

SEARCH

Rows per page 10

1--1 of 1

CONFIG	TIER	CREATED	PRODUCT	MARKETPLACE	ACCOUNT	STATUS
TC-448-764-537 Preview	T1	03/24/2021 3:25 AM	Tutorial Product PRD-640-516-332	Tutorial Marketplace MP-38661	Douglas Becker and Kuh TA-7173-4986-0219	Processing

Rows per page 10

1--1 of 1

CloudBlue Connect © 2021 — Ingram Micro Inc. All Rights Reserved. — [Privacy](#) | [Terms of Service](#) - Version 22.0.1738-gf843fc9

Refer to the Tier Configuration documentation for more information about this module.

Code Snippets

Create a script for processing your Tier Requests as follows:

```

from connect_processor.app.utils.utils import Utils
from cnct import ConnectClient
from typing import Dict

class TierConfiguration:
    # This class is used to manage setup and update tier requests.

    @staticmethod
    def process_request(request, client):
        # type: (Dict, ConnectClient) -> Dict
        # This method processes tier requests in pending status

        # Check the reseller data in the vendor system by calling the Vendor API
        # Use the Vendor API to check, create or update the reseller data in the Vendor Portal
        # The following provides Mock API and client to check tier scope ordering phase parameters:
        # api_client = APIClient(api_url='',
        #                         api_key='')
        # data = {}
        # reseller_info = api_client.check_reseller(data=data)

```



```
tcr_id = Utils.get_basic_value(request, 'id')

# The Vendor API response may have some information that should be saved in fulfillment
# parameters of tier configuration request:
TierConfiguration._save_fulfillment_parameters(request, client)

# In case a tier scope parameter is not valid, the tier request can be switched to the Inquiring
status.
# Therefore, the reseller can check and change provided parameter values.
# Use the following method to assign the Inquiring status:
Utils.set_inquiring_tier_config_request(tcr_id, client)

return Utils.approve_tier_config_request(request, tcr_id, client)
# Once the tier configuration is activated, its associated subscription will be switched to the
Pending state.

@staticmethod
def _save_fulfillment_parameters(request, client):
    # type: (Dict, ConnectClient) -> None
    # This method saves required reseller information in the fulfillment parameters.
    # The payload params IDs should match your product tier fulfillment parameters ID in Connect.
    # The params values should match values provided by the Vendor API.


    tcr_id = Utils.get_basic_value(request, 'id')

    # Prepare the update parameters payload with the response of the APIClient.create_subscription
method
    payload = {
        "params": [
            {
                # Provide the tier fulfillment parameter id as it is configured on the Connect
platform
                "id": "param_a",
                "value": "value for param_a in Vendor System",
                "value_error": "",
                "structured_value": ""
            },
            {
                # Add additional parameters if necessary:
                "id": "param_b",
                "value": "value for param b in Vendor System",
                "value_error": "",
                "structured_value": ""
            }
        ]
    }
```



Summary

As a result, the Processor can be used to successfully approve your Tier Requests. Once a Tier request is approved, its corresponding Tier Configuration is assigned to the *Active* state by the system.



The screenshot shows the CloudBlue Tier Config interface. The top navigation bar includes the CloudBlue logo, a 'Tier Config' dropdown, and links for HELP, a notification icon, and the user profile (Front Street Inc., Vendor - Robert Balboa). The main content area has tabs for 'Tier config', 'DIRECTORY', and 'REQUESTS'. Below the tabs is a table with columns: CONFIG, TIER, CREATED, PRODUCT, MARKETPLACE, ACCOUNT, and STATUS. The table contains one row of data for a configuration named 'TC-448-764-537' with status 'Active'.

CONFIG	TIER	CREATED	PRODUCT	MARKETPLACE	ACCOUNT	STATUS
TC-448-764-537 Preview	T1	03/24/2021 3:58 AM	Tutorial Product PRD-640-516-332	Tutorial Marketplace MP-38661	Douglas Becker and Kub TA-7173-4986-0219	● Active



Note that your Reseller will also receive your Tier Activation Template message. Customize this message via the Embedding section of your product profile page.