



<https://cloudblue.com>

[Documentation](#)  [Developer Resources](#)  [Connect SDK and Tools](#)  [Javascript SDK](#) 

# Class **ConnectClient**



This article has been generated from the online version of the documentation and might be out of date. Please, make sure to always refer to the online version of the documentation for the up-to-date information.

Auto-generated at June 27, 2026



## ConnectClient

*ConnectClient* provides access to resource endpoints of the Cloud Blue Connect Platform.

**Kind:** global class

**Category:** Base

- ConnectClient
  - new ConnectClient(endpoint, apiKey, adapter)
  - .accounts : AccountResource
  - .assets : AssetResource
  - .billingRequests : BillingRequestResource
  - .conversations : ConversationResource
  - .products : ProductResource
  - .requests : RequestResource
  - .hubs : HubResource
  - .recurringAssets : RecurringAssetResource
  - .tierAccounts : TierAccountResource
  - .tierAccountRequests : TierAccountRequestResource
  - .tierConfigs : TierConfigResource
  - .tierConfigRequests : TierConfigRequestResource
  - .webhooks : WebhookResource
  - .listingRequests : ListingRequestResource
  - .cases : CaseResource

### new ConnectClient(endpoint, apiKey, adapter)

Creates a new instance of the Cloud Blue *ConnectClient* class.

Configures the *beforeRequest* hooks to inject the API key in the Authorization header and prefixes the url with the API's base url.

**Returns:** ConnectClient - An instance of the ConnectClient class.

Param	Type	Description
endpoint	string	The base URL for API access.
apiKey	string	The API key to authenticate with Connect.
adapter	AbstractHttpAdapter	An optional adapter.

### connectClient.accounts : AccountResource

Returns an instance of the *AccountResource* class to access



the *Account* resource endpoint.

**Kind:** instance property of `ConnectClient`

#### **connectClient.assets** : `AssetResource`

Returns an instance of the *AssetResource* class to access the *Asset* resource endpoint.

**Kind:** instance property of `ConnectClient`

#### **connectClient.billingRequests** : `BillingRequestResource`

Returns an instance of the *BillingRequestResource* class to access the *BillingRequest* resource endpoint.

**Kind:** instance property of `ConnectClient`

#### **connectClient.conversations** : `ConversationResource`

Returns an instance of the *ConversationResource* class to access the *Conversation* resource endpoint.

**Kind:** instance property of `ConnectClient`

#### **connectClient.products** : `ProductResource`

Returns an instance of the *ProductResource* class to access the *Product* resource endpoint.

**Kind:** instance property of `ConnectClient`

#### **connectClient.requests** : `RequestResource`

Returns an instance of the *RequestResource* class to access the *Request* resource endpoint.

**Kind:** instance property of `ConnectClient`



### **connectClient.hubs** : *HubResource*

Returns an instance of the *HubResource* class to access the *Hub* resource endpoint.

**Kind:** instance property of *ConnectClient*

### **connectClient.recurringAssets** : *RecurringAssetResource*

Returns an instance of the *RecurringAssetResource* class to access the *RecurringAsset* resource endpoint.

**Kind:** instance property of *ConnectClient*

### **connectClient.tierAccounts** : *TierAccountResource*

Returns an instance of the *TierAccountResource* class to access the *TierAccount* resource endpoint.

**Kind:** instance property of *ConnectClient*

### **connectClient.tierAccountRequests** : *TierAccountRequestResource*

Returns an instance of the *TierAccountRequestResource* class to access the *TierAccountRequest* resource endpoint.

**Kind:** instance property of *ConnectClient*

### **connectClient.tierConfigs** : *TierConfigResource*

Returns an instance of the *TierConfigResource* class to access the *TierConfiguration* resource endpoint.

**Kind:** instance property of *ConnectClient*

### **connectClient.tierConfigRequests** : *TierConfigRequestResource*

Returns an instance of the *TierConfigRequestResource* class to access the *TierConfigurationRequest* resource endpoint.



**Kind:** instance property of `ConnectClient`

**`connectClient.webhooks` : `WebhookResource`**

Returns an instance of the `WebhookResource` class to access the `Webhook` resource endpoint.

**Kind:** instance property of `ConnectClient`

**`connectClient.listingRequests` : `ListingRequestResource`**

Returns an instance of the `ListingRequestResource` class to access the `ListingRequest` resource endpoint.

**Kind:** instance property of `ConnectClient`

**`connectClient.cases` : `CaseResource`**

Returns an instance of the `CaseResource` class to access the `HelpdesCase` resource endpoint.

**Kind:** instance property of `ConnectClient`